Fiery JobFlow Pro installation guide

Fiery JobFlow Pro provides a browser-based prepress workflow that allows you to define and automate repetitive tasks such as PDF conversion, preflight, correction of PDF files, image enhancement, document imposition.

Fiery JobFlow Pro can be installed on Windows Server 2025, Windows 11 23H2 (version and later) client computers, and on Fiery servers with FS700 system software and later running Windows 10 LTSC.

Fiery JobFlow Pro system requirements

For system requirements, see https://assistance.fiery.com/jobflowpro/specs/.

Fiery JobFlow Pro installation option

Fiery Command WorkStation 7.1 and later, and Fiery Impose are required to use the fiery-impose node in Fiery JobFlow Pro Editor.

Install Fiery JobFlow Pro

Before you begin, make sure you are logged in to your Fiery Account.

JobFlow Pro is installed using Fiery Software Manager, which is part of the Fiery Workflow Applications.

1. Open Fiery Software Manager.
2. Click **Install** next to JobFlow Pro.

   After the installation is complete, a JobFlow Pro shortcut is created on your desktop.

   Note: During installation of JobFlow Pro, the installer automatically detects the drive which has more free space and creates a folder called JobFlowProFolders. The folder contains subdirectories for Drop Zones, Hot Folders, and imported resources. If you are upgrading from Fiery JobFlow Pro v1.0 to Fiery JobFlow Pro v1.1, your existing workflow resources are automatically migrated to the new Resources folder.

Activate the JobFlow Pro license

Fiery JobFlow Pro requires a license that must be activated from the Fiery JobFlow Pro home page.

1. Double-click the JobFlow Pro shortcut on your desktop.

© 2026 Fiery, LLC.
15 November 2026

45275242

2 Sign in to Fiery JobFlow Pro as Admin, and type the new password in the **Password** field.

Note: The password must be 8 to 20 characters long and include at least one uppercase letter, one lowercase letter, one number, and one special character. If these requirements are not met, the requirements are displayed in red until the password is valid.

3 Type the password again in the **Confirm password** field.

4 Click **Sign In**.

5 In the **Recovery Key** window, copy or download and securely save the 20-character recovery key.

Note: The recovery key is required to reset the administrator password. Save the recovery key in a secure location.

6 Select the **I have saved this recovery key securely** check box, and click **OK**.

7 Click **Add license** in the window that appears.

8 On the **License activation** page, click **Activate**, and then click **Continue** to agree to the terms and conditions of the license agreement.

9 Type your License Activation Code (LAC) in the field and click **Continue**.

10 Click **Activate**.

11 Click **Finish**.

12 Return to the Fiery JobFlow Pro home page and refresh the page to access the licensed version.

If the activation requires a restart, you can either click **Restart** to restart now or click **Finish** if you want to activate additional options before restarting. If the activation does not require a restart, click **Finish**.

Note: Only users with the Admin role can add a license. If the license is not activated, users with the Operator role are prompted to contact the administrator.

Updating Fiery JobFlow Pro

Fiery Software Manager manages updates to Fiery JobFlow Pro. To access the latest features, fixes, and enhancements, keep Fiery JobFlow Pro updated to the latest version.

Uninstalling Fiery JobFlow Pro from a Windows computer

You can uninstall Fiery JobFlow Pro from a Windows computer through Windows or the Fiery Software Manager.

Note: When you uninstall Fiery JobFlow Pro, the application components and default JobFlowProFolders directories (including imported resources and temporary processing files) are removed from the computer. To preserve your workflows and imported resources, back up your data from the Settings tab in Fiery JobFlow Pro before uninstalling.

Uninstall Fiery JobFlow Pro in Windows Settings

1 From the Windows desktop, right-click the **Start** button.

2 Click **Settings** > **Apps**.

3 Click **Installed apps**.

4 Click the **More options** icon next to Fiery JobFlow Pro.

5 Select **Uninstall**.

6 Follow the on-screen instructions.

Uninstall Fiery JobFlow Pro in Fiery Software Manager

1 From the Windows desktop, click Fiery Software Manager.

2 Click the **Remove** icon next to Fiery JobFlow Pro.

3 Follow the on-screen instructions.

Install Fiery Model Hub

Fiery Model Hub allows local AI use with Fiery JobFlow Pro workflows on a Mac computers without requiring cloud connectivity or API keys.

Before you begin, make sure your Mac computer is equipped with an M4 chip or later, is running macOS 26 or later, has at least 32 GB of RAM, and is connected to the same local network as the Fiery JobFlow Pro server.

1 Download the Fiery Model Hub.dmg onto the Mac client computer, and then double-click it to extract the contents.

2 Double-click the Disk Image file, Fiery Model Hub.dmg, to mount it.

3 Double-click the Fiery Model Hub Installer.pkg and follow the on-screen instructions to finish the installation.

4 Follow the on-screen instructions to complete the installation.

After installation, Fiery Model Hub runs as a background service.

Initial startup of Fiery Model Hub

After installing Fiery Model Hub, you must start the application to complete the initial setup and download the required default model files.

Make sure the Mac computer has an active internet connection.

1 Open the **Applications** folder.

2 Double-click **Fiery Model Hub**.

3 Click **Get Started**.

4 Select the default Port or modify it as needed.

5 Click **Start Server**.

6 Click **Done**.

Allow the initial startup process to finish without interruption.

7 Click the **Fiery Model Hub** icon in the menu bar to verify that the status displays **Running**.

8 Download the model files in the **Presets** tab.

After the status displays **Running**, you can connect Fiery Model Hub to Fiery JobFlow Pro. For more information, see *Fiery JobFlow Pro Help*.

Uninstalling Fiery Model Hub from a Mac computer

You can uninstall Fiery Model Hub from a Mac computer through Fiery Software Uninstaller or by manually deleting the application and its related files.

Uninstall Fiery Model Hub using Fiery Software Uninstaller

You can use Fiery Software Uninstaller to uninstall Fiery Model Hub.

Before you begin, make sure that Fiery Model Hub is not being used by any Fiery JobFlow Pro jobs.

The Fiery Software Uninstaller utility must be installed on the Mac client computer.

Note: Fiery Model Hub version 1.0 does not include the Fiery Software Uninstaller.

1 Open theApplications folder.

2 Double-click the **Fiery Software Uninstaller** icon.

3 Select **Fiery Model Hub** from the list of installed applications.

4 Click **Uninstall**.

Uninstall Fiery Model Hub manually

You can manually uninstall Fiery Model Hub.

Before you begin, make sure that Fiery Model Hub is not being used by any Fiery JobFlow Pro jobs.

1 Open the Applications folder.

2 Open the Fiery folder.

3 Select **Fiery Model Hub** and delete the application in one of the following ways:

- Drag the **Fiery Model Hub** application to the **Trash** icon.
- Right-click the **Fiery Model Hub** application and select **Move to Trash**.
- Click **File** > **Move to Trash**.

4 Open **Finder** and delete the folders located at the following locations:

- /Users/<User>/.fiery-model-hub
- /Library/Application Support/Fiery/Fiery Model Hub/
- /Library/LaunchAgents/com.fiery.modelhub.plist
- /Library/Preferences/EFI/com.efi.packageversion.plist

Accessing Fiery JobFlow Pro Help

To access *Fiery JobFlow Pro Help*, sign in to Fiery JobFlow Pro and click **Help** from the profile icon located in the top right corner of the Fiery JobFlow Pro webpage.

For additional information or support, registered users may start a discussion through Fiery Communities.