



Dlican

Dlican are proof / production printers.

This document provides information on how to drive the printers from Fiery XF.

Installation requirement:

- Fiery XF 9.0.2
- Fiery Command WorkStation 7.2 or higher

Supported printers

The following drivers exist:

Printer model	Color Modes
Dlican DLI-2513 Ricoh Gen5	KCMY, KCMYLcLm, KCMYOB, KCMYLcLmLkLLk, KCMYLcLmLkO, KCMYLcLmLyLk
Dlican DLI-2513 Ricoh Gen6	KCMY, KCMYLcLm, KCMYOB, KCMYLcLmLkLLk, KCMYLcLmLkO, KCMYLcLmLyLk
Dlican DLH-2513 Ricoh Gen5	KCMY, KCMYLcLm, KCMYOB, KCMYLcLmLkLLk, KCMYLcLmLkO, KCMYLcLmLyLk
Dlican DLH-2513 Ricoh Gen6	KCMY, KCMYLcLm, KCMYOB, KCMYLcLmLkLLk, KCMYLcLmLkO, KCMYLcLmLyLk
Dlican DLB-2513 Ricoh Gen5	YMCK, YMCKLcLm, YMCKOB, YMCKLcLmLkLLk, YMCKLcLmLkO, YMCKLcLmLyLk
Dlican DLB-2513 Ricoh Gen6	YMCK, YMCKLcLm, YMCKOB, YMCKLcLmLkLLk, YMCKLcLmLkO, YMCKLcLmLyLk

License


Dlican models are supported by Printer Option Group 6 license.

Supported Max Width: 2500mm x1300mm

Connection Type: IP Network/File Output


Setting up the printer in Fiery XF:

1. Set up the export path in Server Manager to generate a *.prn file which you can load into the Dlican Printer software.



The 'NEW PRINTER' dialog box shows the 'Connection type' set to 'File output'. The 'Export path' is 'C:\ProgramData\Fiery\Fiery XF\Server\Export\Dlican', with a 'Choose...' button. The 'Naming' dropdown is set to '%order_%job_%jobid_%t_%p_%date', with an information icon and an example: '001_FileName_1_T1_P1_20260706181322'. At the bottom are '< Back', 'Finish', and 'Cancel' buttons.

2. Set up the IP address in Server Manager to connect to printer.



The 'NEW PRINTER' dialog box shows the 'Connection type' set to 'Print via IP network'. The 'IP Address' field contains '127.0.0.1'. Under 'Used TCP/IP protocol is', 'RAW on port' is selected with a port number of '9100', and 'LPR queue' is unselected. The 'Speed' section has 'RIP and print on the fly' unselected. At the bottom are '< Back', 'Finish', and 'Cancel' buttons.

Settings

Resolutions

The drivers offer the following resolutions:

Dlican DLI-2513: 720x150, 720x300, 720x600, 720x900, 720x1200, 720x1500, 720x1800, 720x2400, 720x3000, 726x150, 726x300, 726x600, 726x900, 726x1200, 726x1500, 726x1800, 726x2400, 726x3000, 960x150, 960x300, 960x600, 960x900, 960x1200, 960x1500, 960x1800, 960x2400, 960x3000, 1270x150, 1270x300, 1270x600, 1270x900, 1270x1200, 1270x1500, 1270x1800, 1270x2400, 1270x3000.

Dlican DLH-2513: 635x150, 635x300, 635x600, 635x900, 635x1200, 635x1500, 635x1800, 635x2400, 635x3000, 720x150, 720x300, 720x600, 720x900, 720x1200, 720x1500, 720x1800, 720x2400, 720x3000, 960x150, 960x300, 960x600, 960x900, 960x1200, 960x1500, 960x1800, 960x2400, 960x3000, 1200x150, 1200x300, 1200x600, 1200x900, 1200x1200, 1200x1500, 1200x1800, 1200x2400, 1200x3000.


Dlican DLB-2513: 479x360, 479x720, 479x1080, 479x1440, 479x2160, 479x2880, 540x360, 540x720, 540x1080, 540x1440, 540x2160, 540x2880, 726x360, 726x720, 726x1080, 726x1440, 726x2160, 726x2880.

Print modes

The driver offers **Standard** print mode.

Dot sizes

Dot size:



S, M, L stands for Small, Middle, Large dot.

Dot Size	Purpose
SML	Lowest resolution or high ink medium
ML	Higher head distance
SL	Anti-banding measure
SM	Middle resolution
Large	Highest head distance
Middle	Higher head distance, middle resolution
Small	High resolution